How to configure the login module?

help.fracttal.com/hc/en-us/articles/25022708978701-How-to-configure-the-login-module

From Fracttal One, the asset and maintenance management platform, we have functionality that allows users to customize their login experience. This feature allows you to define the default login module for each user, providing greater control and flexibility.

This allows users to customize their experience and have faster access to the areas of the platform they use the most. Let's take a closer look at how this feature works and how it applies to different user profiles.

Default Login Module Configuration:

To access this functionality, users must follow the steps below:

1. Click on the top right where your name appears in Fracttal One.



2. Click on configuration



3. In the menu on the left side click on user account

E Settings				JC 😵 😵	~
Activación Fracttal - Español - 477				6 s	ave
ନ୍ତି General		දිදු User Accounts		Permissions	
& User Accounts	User Accounts 86 / 100	Limited technician accounts 17 / 50	Request accounts 12 / Unlimited	Number of read only accounts 1 / Unlimited	
j≝ Modules				0 = \$:
(8) Financial	Enabled	Name 个	Email J		Use ⊐
Auxiliary Catalogs	Yes	ALEXANDER		@gmail.com	Tł
Document Management	O Yes	Alexander		;@fracttal.com	In
Transitions en	O Yes	Alexander		@gmail.com	In
I ransactions Log	O Yes	Alexander)fracttal.com	In
G Security	☐ Yes	ALEXANDER		@fracttal.com	Τŀ
🐻 API Connections	O Yes			gmail.com	In
🕠 Guest Portal	O Yes			[:] racttal.com	In
Account	Showing 50 of 116				

4. Select the personnel of your interest.

				B	JC	~
Activación Fracttal - Español - 477					6	Save
General		User Accounts		Permissions		
& User Accounts	User Accounts	Limited technician accounts	Request accounts	Number of read on	ly accounts	5
🛗 Business Calendar	86 / 100	17 / 50	12 / Unlimited	1 / Unlimited		
🚛 Modules				0		:
Sinancial	Enabled	Name 个	Email			Use
Auxiliary Catalogs	Ves	Jonas Campos		@fracttal.com		In
🕒 Document Management	Yes					
Transactions Log	O Yes					
G Security	O Yes					
G API Connections	Yes					
Guest Portal	O Yes					
Account	Showing 100 of 116					

5. There you will find a field called "Default Login Module Configuration".

nnouse Personnel			- Er	nabled
Name		Email		
Jonas Campos	~ X			
Profile		Group Permissions		
Administrator	~	Administrator		
only active Assets				
ocation				~

- 6. In this field, the following functions can be defined:
- 1. "Allow Edit by User."
- 2."Display Main Dashboard."

3."Module."

← Edit User account

Inhouse Personnel		Enabled
Name	~ X	Email ;@fracttal.com
Profile Administrator	~	Group Permissions Administrator
iguring the main module for log	jin	- Module Dashboard ~
1	2	3
1 w only active Assets Location	2	3

Detail:

1. Allow Edit by User: This option allows the user to select their own default login module, giving them full control over these settings.

2. Display Main Dashboard: With this option enabled, the display of the main Fracttal Dashboard is restricted, which can be useful for users who only need access to certain parts of the platform.

3. Module: This feature allows the user to select the module they wish to open as the default login. However, the options available will be restricted according to the active modules assigned to the user's permission group.

Considerations by User Profiles:

The default login module selection functionality applies differently to various user profiles in Fracttal. These considerations are detailed below:

Administrator:

- "Allow Edit by User" is predefined as enabled.
- "Display Main Dashboard" is predefined as enabled.
- "Module" allows you to select the desired module as the default login.

Customized:

- "Allow Edit by User" is a selectable option.
- "Display Main Dashboard" is a selectable option.
- "Module" allows you to select the desired module as the default login.

Technician:

- "Allow Edit by User" is a selectable option.
- "Display Main Dashboard" is a selectable option.
- "Module" allows you to select the desired module as the default login.

Limited Technical:

- "Allow Edit by User" is predefined as disabled.
- "Display Main Dashboard" is predefined as disabled.
- "Module" is predefined as "Work Orders".

Reading only:

- "Allow Edit by User" is a selectable option.
- "Display Main Dashboard" is a selectable option.
- "Module" allows you to select the desired module as the default login.

Applications:

- "Allow Edit by User" is predefined as disabled.
- "Display Main Dashboard" is predefined as disabled.
- "Module" is predefined as "Request".

These permissions provide users with greater control over their experience on the platform. It allows for effective customization according to each user's needs and responsibilities, improving efficiency and convenience when accessing key Fracttal functions. This feature is especially beneficial for administrators and users who wish to tailor their experience on the platform according to their specific needs.