

How to configure the login module?


help.fractal.com/hc/en-us/articles/25022708978701-How-to-configure-the-login-module

In Fractal One, users can customize their login experience by setting the module that will open by default. This allows them to access the areas of the platform they use most often more quickly. Below, we explain how to configure this option.


Default Login Module Configuration:

To access this functionality, users must follow the steps below:

1. Click on the top right where your name appears in Fractal One.



2. Click on configuration



3. In the menu on the left side click on user account

The settings page shows the 'User Accounts' section. The left sidebar has 'User Accounts' highlighted. The main content area displays a table of user accounts.

User Accounts		Permissions	
User Accounts 86 / 100	Limited technician accounts 17 / 50	Request accounts 12 / Unlimited	Number of read only accounts 1 / Unlimited
Enabled	Name	Email	Use
☐	ALEXANDER	@gmail.com	TI
☒	Alexander	:@fractal.com	In
☒	Alexander	@gmail.com	In
☒	Alexander	:@fractal.com	In
☒	ALEXANDER	@fractal.com	TI
☒		gmail.com	In
☒		:ractal.com	In

Showing 50 of 116

4. Select the personnel of your interest.

Settings

Activación Fractal - Español - 477

Save

General

User Accounts

Business Calendar

Modules

Financial

Auxiliary Catalogs

Document Management

Transactions Log

Security

API Connections

Guest Portal

Account

User Accounts

Permissions

User Accounts	Limited technician accounts	Request accounts	Number of read only accounts
86 / 100	17 / 50	12 / Unlimited	1 / Unlimited

Enabled	Name	Email	Use
☐	Yes		
☐	Yes	Jonas Campos	@fractal.com
☐	Yes		
☐	Yes		
☐	Yes		
☐	Yes		
☐	Yes		
☐	Yes		

Showing 100 of 116

5. There you will find a field called "Default Login Module Configuration".

Edit User account

User Type

Inhouse Personnel

Enabled

Name

Jonas Campos

Email

Profile

Administrator

Group Permissions

Administrator

Configuring the main module for login

Allow user editing

Viewing main dashboard

Module

Dashboard

Show only active Assets

Location

//

Other Options

Authentication only by Single Sign-On

Receive email notifications

6. In this field, the following functions can be defined:

1. "Allow Edit by User."
- 2."Display Main Dashboard."
- 3."Module."

← Edit User account

User Type
Inhouse Personnel

Enabled

Name
Jonas Campos

Email
;@fracttal.com

Profile
Administrator

Group Permissions
Administrator

Configuring the main module for login

☒ Allow user editing

☒ Viewing main dashboard

Module
Dashboard

Show only active Assets

Location
//

Other Options

☐ Authentication only by Single Sign-On

☒ Receive email notifications

Detail:

1. Allow Edit by User: This option allows the user to select their own default login module, giving them full control over these settings.

2. Display Main Dashboard: With this option enabled, the display of the main Fracttal Dashboard is restricted, which can be useful for users who only need access to certain parts of the platform.

3. Module: This feature allows the user to select the module they wish to open as the default login. However, the options available will be restricted according to the active modules assigned to the user's permission group.

Considerations by User Profiles:

The default login module selection functionality applies differently to various user profiles in Fractal. These considerations are detailed below:

Administrator:

- "Allow Edit by User" is predefined as enabled.
- "Display Main Dashboard" is predefined as enabled.
- "Module" allows you to select the desired module as the default login.

Customized:

- "Allow Edit by User" is a selectable option.
- "Display Main Dashboard" is a selectable option.
- "Module" allows you to select the desired module as the default login.

Technician:

- "Allow Edit by User" is a selectable option.
- "Display Main Dashboard" is a selectable option.
- "Module" allows you to select the desired module as the default login.

Limited Technical:

- "Allow Edit by User" is predefined as disabled.
- "Display Main Dashboard" is predefined as disabled.
- "Module" is predefined as "Work Orders".

Reading only:

- "Allow Edit by User" is a selectable option.
- "Display Main Dashboard" is a selectable option.
- "Module" allows you to select the desired module as the default login.

Applications:

- "Allow Edit by User" is predefined as disabled.
- "Display Main Dashboard" is predefined as disabled.
- "Module" is predefined as "Request".

These permissions allow users to customize their experience in Fractal One based on their needs and responsibilities, making it easier to access the features they use most often. This is

especially useful for administrators and users who need to personalize their access to the platform.